

# Set machine parameters

You can find this function under

**Settings/Card system/Set vending machine parameters**

Here you will find the most important settings for your card readers at vending machines, doors or other locations. As the PC CADDIE.id card system can be used for a wide variety of applications, the term „vending machine“ is used in the following.



When installing the card system, our support will make these settings for you. Please do not change them if you are unsure. We will be happy to answer any questions you may have.

## Overview of vending machines

**Settings/Card system/Set vending machine parameters**

1 Automat	2 System	3 PC	4 Read	5 Add.	6 Perm.	7 Price	8 Article	9 Activity
TeeTime Automatic	990001	1				GRATIS		
Ball machine1	990001	2/11		P01	B	BALL		OFF:03.03.00/12:40

1. Designation of the machine, e.g. „Ball machine 1“, „Ball machine 2“ or „Door caddie hall“. You can immediately recognise which card reader is involved from the machine name. It is freely selectable.
2. System number: This corresponds to your DGV number, which is stored in PC CADDIE (country code + club number).
3. Control PC number / connection port
4. Reader number: Each card reader has a unique reader number, which may only be assigned once.
5. Address: Unique address of your card reader. Each address within a data bus may only be assigned once. On some machines, the address must be set using DIP switches.
6. Authorisation code: e.g. „B“ for the ball machine, „H“ for the door of the men's cloakroom and „D“ for the door of the ladies' cloakroom. PC CADDIE uses this authorisation to recognise who is

- allowed to open the door or use the machine. This is particularly necessary for access systems.
7. Abbreviation of the stored price scheme. Door access is usually free of charge, whereas a monetary value is to be booked for withdrawal from the ball machine.
  8. Stored item for each vending machine. This is posted to the respective person's sales account when the card reader is successfully used.
  9. Under „Activity“ in an online system, you can see whether the card reader is ONLINE or OFFline. You can also see this from the stored colour (green = online, red = offline), similar to the [Vending machine control window](#).

## Create/edit new vending machine

Below you will find information on creating/editing a vending machine.

A distinction must be made between an online and offline system.

### PC CADDIE.id online system

Edit a machine via the button **Edit (F7)** or create a new machine via the **New machine (F9)** button to create a new vending machine.

**Automat configuration** [X]

1 Name: Ball machine 1

2 Club number: 499001

3 Control system: 1 Reader no.: 1 4

5  Deactivated

6 Permission area: B Room no.: 7

8 Connection: MOXA-TCP/IP: 192.168.178.201:2

9 Reader type: Quio Address: 01

10 Serial number: 58100046

11 System type: Factor automat 5;20

12 Accounting article: ba1 Ball machine 1 [Print] [Help]

13 Green fee article: ba1r Ball machine 2 rangt [Print] [Help]

14 Price scheme:

Ball machine	BALL
Gratis	GRATIS
Simulator	SIMU

[+] New (F9)

[O] Edit (F7)

[X] Delete (F5)

Ping network interface (F3)

Webinterface connector (F4)

Settings Offline system

Ok

Cancel

1. Select a **designation** for your machine, e.g. „Ball machine 1“
2. The **club number** is automatically entered by PC CADDIE, please do not change it.
3. Number of the **control system**. A separate PC CADDIE card server is responsible for each number. If you have a large number of vending machines, it makes sense to install several control systems - however, one is usually sufficient.
4. Each vending machine receives its own **reader number**
5. Here you can temporarily **deactivate** when it is not in operation
6. **authorisation**. „B“ for ball machine or „C“ for the door at the caddie hall. Each authorisation area, each authorisation group has its own identifier (capital letter or number 1-9)
7. **Room number** for an access reader in the hotel
8. **Connection** if the converter for the card reader is directly connected serially, enter the COM port here. However, RS485/LAN converters are usually used, so select „Moxa/TCP/IP“ here and enter the TCP/IP address of the converter and the port number.
9. Depending on the read head used, set the **reader type** and the **reader address** here.
10. **Serial number** of the reader (only required for reader type „Quio“)
11. The **system type** depends on whether it is a ball machine, a door or a vending system, for

example. These settings are also very specific - we would like to mention the two most common variants here:

1. For a ball vending machine, set „Factor vending machine“ and behind it „2;20“. These values are variable and mean that a maximum of 2 draws of 20 balls each are dispensed at one time on this machine. This setting is useful if a maximum of 40 balls fit into a ball basket. The maximum factor and the number of balls are separated by a semicolon.



Please note that the actual number of balls per delivery is set on the vending machine itself. PC CADDIE only shows the number set in the vending machine configuration as information on the reader display.

2. For a door, for example, set „Lock“ and „10“. In this case, the door would remain open for 10 seconds.
12. **Booking article** for the machine. Each „successful“ triggering by the reader (ball release, opening the door, etc.) books this [article directly into the sales account](#) of the respective person. If you wish, this field can also be left blank if you do not want each (free) opening of a door reader to be booked with an article.
13. **Green fee article:** [Article for booking the green or range fee](#). If you do not need to book a range fee at the machine, simply leave this field blank.
14. **Price scheme** which applies to this machine. [Edit price scheme](#)

## PC CADDIE.id Offline System

The PC CADDIE.id Offline System consists of 3 components. The **CPU (minicomputer)** is the control centre, the **read head** the communication path and the **CF card** is the storage medium that stores the vending machine settings and sales. To configure the desired parameters, edit a vending machine using the button **Edit (F7)**

### System

**Offline card reader** [X]

Remote access | Administration

System | Configuration | Numbers activation | Opening duration | Articles and Prices | Display

1 Description: Door1 Offline

2 Club no.: 494421 14421

3 Reader no.: 12

4 Access area: B Room no.:

5 CPU serial no.: 185732

6 Reader serial no.: 51033565

7  Set date and time: Date 30.06.15 Time 14:56

8  Sound signals for reader

9  WatchDog Set 0 Wait 0

File: 0494421\READER12\AUTO\PCC\_AUTO.INI

OK Cancel

1. Select a **designation** for your machine, e.g. „Ball machine 1“
2. The **club number** is automatically entered by PC CADDIE and cannot be changed. Additional club numbers can be activated in a multi-club system using the search function.
3. Each vending machine receives its own **reader number**
4. **authorisation code**. „B“ for ball machine or „C“ for the door at the caddie hall. Each authorisation group has its own identifier (capital letter or number 1-9)
5. Enter the **serial number of the CPU** (control PC of the offline system) here.
6. Serial number of the reader
7. Enter the **date** and the **time** time. Please ensure that the time corresponds to the actual time at which you start the offline system with the PC CADDIE.id Memory Card. PC CADDIE suggests a time that is 15 minutes in the future.
8. Use this tick to activate or deactivate the **sound signals** on the reader.
9. The offline system offers the option of activating a „watchdog“. It monitors the offline system and restarts it if it no longer responds.

## Configuration

The screenshot shows the 'Offline card reader' configuration window. The 'Administration' tab is selected, and the 'Configuration' sub-tab is active. The configuration fields are as follows:

- Function:** A dropdown menu set to 'Factor automat' (1).
- Factor automat:**
  - Maximum:** A text input field containing '5' (2).
  - Standard:** A text input field containing '1' (3).
  - Balls per purchase:** A text input field containing '23' (4).
  - Wait time between purchases:** A text input field containing '7' (5).
  - Wait time reference factor:** A text input field containing '4' (6).
- Lock (door):**
  - Opening period:** A text input field containing '7' (7).
- Activate relais:** A dropdown menu set to 'Connect relais to CPU and read head' (8).
- Admin-PIN:** A text input field followed by the text 'for calling an Admin menu on the reader' (9).
- Global-PIN:** A text input field followed by the text '(customizable in the Admin menu on the reader)' (10).
- PIN-List:** A text input field (11).

On the right side of the window, there are two buttons: 'OK' (with a green checkmark icon) and 'Cancel' (with a red 'X' icon).

- Function** Determine which function the offline system has. When operating on a ball vending machine, „Factor vending machine“ is selected - for a door, please select „Lock“. The „Factor machine with opening time“ function is rarely required in the case of a machine with factor selection, which requires a longer relay circuit for triggering. For a door (function:Lock), you can skip the next points and continue with point **7** continue reading.
- From here, you make the settings for a ball machine (factor machine). With **Maximum** you determine the maximum selectable factor on the reader. In the example, 5 ball withdrawals are possible at once by the customer first pressing the **5** on the reader and then holding their Mifare chip in front of the reader. For ball baskets that can hold a maximum of two covers, set a maximum of **2** here.
- Standard**-Factor for triggering without factor selection at the reader. The customer only holds their card in front of the reader. Set a **2** here if you want two triggers to occur each time the Mifare chip is presented.
- Number of **balls per reference**. This number of balls is shown on the reader display depending on the reference factor. This is for the customer's information only and does not change **not** the number of balls that the machine dispenses per release. If you would like to change the actual number of balls dispensed by the machine, please contact your machine manufacturer.
- Waiting between draws** This is the time in seconds during which no new draw is possible and the time until the earliest next release. If the customer makes two ball pulls at the reader, i.e. factor **2** is selected at the reader, PC CADDIE waits for this time with the second circuit. This can be set differently depending on the ball machine, as some machines accept the next activation after just 2 seconds, while others may only accept it after 6 seconds. Please contact your machine manufacturer for more information.

6. With **Waiting time of the reference factor** you specify the time in seconds during which the factor selected by the customer remains active. If the Mifare chip is not held in front of the reader within this time, the factor selection is cancelled and the reader returns to its initial state.
7. **Opening time** in seconds for switching the relay/door opener or for switching a „factor machine with opening time“.
8. The PC CADDIE.id offline system is equipped with two potential-free relays. One is located on the CPU and one on the back of the reader. Configure here which **relay is to be activated** should be activated. With „1:Read head, 2:CPU“, for example, you also have the option of activating the relay by pressing buttons **1** or **2** on the reader to select which relay is to be switched - this may be necessary for vending machines with two switching inputs, where different operating times are triggered depending on the relay circuits used (lighting system, solarium, etc.).
9. Set the **admin PIN** must be defined. You can use this to make administrative settings directly on the reader (setting the time/date, DEBUG mode for extended logging, changing the global PIN). This PIN must be numeric and should have 4-6 digits.
10. With the **global PIN** you have the option of triggering free switching by entering a PIN. This can be useful for employees who do not want to use a card to open the door. At a ball machine, this PIN could be used to dispense balls for a Pro. For security reasons, however, we strongly recommend that you only work with Mifare chips at the ball machine. The global PIN can be changed directly on the reader after entering the admin PIN.
11. Specify one or more PINs (comma-separated) with which you want to open a door. This option can be useful on tournament days, for example, when you want to give guests access to the cloakrooms without a Mifare card. PINs from this list cannot be customised on the reader and can be changed at any time via this configuration.

## Number activation

**Offline card reader**

Remote access | Administration

System | Configuration | **Numbers activation** | Opening duration | Articles and Prices | Display

The following options allow the activation of groups of cards, without being necessary to program each card individually.

The automat (lock/door) opens for each such card, WITHOUT any charges, so the usage is free!

Activation:  **1**

Club numbers:  **2**

**3**  Check the date of the card (only DGV!)

**4**  Days of validity

Individually blocked cards are always rejected, even if they fulfill these conditions

OK

Cancel

Groups of cards can be generally activated here without having to be individually programmed in PC CADDIE beforehand.



This option is useful for doors where you want to grant access to all members, for example. You should not activate this option for vending machines that charge a fee (ball machine), as every withdrawal is free of charge via the flat-rate number activation!

1. Activate the activation for **individual member numbers** one or more **club numbers** or **all DGV cards**. If you do not wish to activate the blanket number activation, please leave this setting at **none** setting.
2. Enter the authorised membership or club numbers here, separated by commas. **0499001**  
Allows all club 9001 cards.
3. With this option you decide whether the date of the DGV card should be checked...
4. ...and how many days after the expiry date the DGV card will still be authorised.

## Permanently open

Up to 8 time periods can be activated in which the machine keeps the relay switched continuously. For example, to keep doors open at certain times. The opener of the door must support continuous operation for this.

## Articles and prices

This is where the [items](#) are assigned and the prices defined. Please note that the assigned ball and green fee articles must always have the value 0. The price is only defined via the price scheme. [Edit price scheme](#)

Attention! The [price scheme highlighted in blue](#) is valid for the selected machine. So if you accidentally select the price scheme for a ball machine **Free** is selected by mistake, every ball withdrawal is free of charge.


## Display

Here you can enter the texts to be shown on the display and set the display switchover time.

## Remote enquiry

Here you can activate remote control of the offline system if it is equipped with a radio modem and allow the remote release of balls.

## Administration



An update for offline systems can be loaded here. Or an empty CF card can be assigned to the machine. The other functions are for special purposes and are usually only required by PC CADDIE support.

## Questions and answers



Where can I see if it is offline system version 1.25?

You cannot see this directly, but the VER macro displays the date of the offline system version when the offline system is installed. For example like this:

```
Offline-System: 27.06.1117:21:10
```



Where should I click when the CF card is inserted?

The „Configure vending machine“ dialogue must be open (to be found under **Settings/Card system/Set vending machine parameters**). A window will pop up as soon as Windows and PC CADDIE have recognised the card.



What do I have to do if WINDOWS does not recognise the CF card?

In a local installation, it is best to terminate the CF card reader using the Windows „Eject“ function, remove the CF card and remove the CF card reader plug from the USB interface and reinsert it.

In a TERMINAL session, log off the session and carry out the same procedure as for a local installation, then reconnect the terminal session.

## Edit pricing scheme

The costs for the purchase of balls or a release at a vending machine are defined exclusively in the pricing scheme:

**Configuring Price-Range**

Description:  Short form:

Stage	Booking	Green fee	Credit	Points	Unit	Zone	Blocked
1 - Member	<input type="text" value="1,50"/>	<input type="text" value="0,00"/>	<input type="text" value="50,00"/>	<input type="text" value="1"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input type="checkbox"/>
2 - Guest	<input type="text" value="2,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="1"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input type="checkbox"/>
3 - Youth - discount	<input type="text" value="1,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input type="checkbox"/>
4 - Service	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input type="checkbox"/>
5 - Employee	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input type="checkbox"/>
6 -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
7 -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
8 -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
9 -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
A -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
B -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
C -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
D -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
E -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
F -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>

Exception period 1    Exception period 2    Exception period 3

OK    Cancel

The PC CADDIE pricing is based on the card type (level). The card type is not related to the membership features.



A different price (**booking**) for a purchase at a vending machine (e.g. ball purchase). For doors, the price usually remains at 0.00. You will find the predefined price scheme GRATIS in PC CADDIE.

In addition, the column **green fee** column to request a further payment (e.g. range fee). By default, the **green fee** charged once per day; however, it is also possible to pay the **green fee** every time you play.

The column **Credit** column enables withdrawals to be made on credit at the machine. Withdrawals are made up to the specified limit and posted directly to the OP account [Open item postings](#) .

Under the column **Points** column indicates how many points are deducted from a credit balance per withdrawal.



PC CADDIE always debits all points first before claiming the cash value of the card.

The columns **bar** and **zone** columns are for very specific settings and should only be changed by PC CADDIE support.

Via the buttons **Exception period 1 to 3** buttons can be used to define time-limited exceptions.

**Configuring Price-Range exceptions**

Days:  Mo  Tu  We  Th  Fr  Sa  Su  
 On bank holidays

Time:  o'clock to  o'clock

Stage	Booking	Green fee	Credit	Points	Unit	Zone	Blocked
1 - Member	<input type="text" value="1,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input type="checkbox"/>
2 - Guest	<input type="text" value="2,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input type="checkbox"/>
3 - Youth - discount	<input type="text" value="0,50"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input type="checkbox"/>
4 - Service	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input type="checkbox"/>
5 - Employee	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input type="checkbox"/>
6 -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
7 -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
8 -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
9 -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
A -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
B -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
C -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
D -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
E -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>
F -	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0,00"/>	<input type="text" value="0"/>	<input type="text" value="00:00"/>	<input type="text" value="0"/>	<input checked="" type="checkbox"/>

OK  
Cancel

The exceptions can be set by day and time. If there are several overlapping exceptions, PC CADDIE always takes the most favourable variant for the person making the booking.



In the event of an incorrect, active exception without price assignment, the ball bookings would therefore be made free of charge. Be careful with these settings.

## Data synchronisation with the PC CADDIE.id Memory Card





This synchronisation only applies to the offline system.

The CF card is the storage medium of the PC CADDIE.id offline system. All parameters are saved on it during the initial configuration and the ball bookings are saved during use. It must be read out regularly so that the bookings are transferred to PC CADDIE.

## Initial Installation


After inserting the CF card into the CF card reader, the menu item **Administration/Install new CF card** is called up.



PC CADDIE now copies the current version of the offline system and the parameters to the CF card.



Double-click on the selected ball machine or on **Edit** then the menu opens automatically CF card:



Here, the menu item **Data synchronisation with the CF card** menu item, the bookings are imported into PC CADDIE and the current configuration is written to the CF card at the same time.

Under **Edit settings** you can change the system parameters.

**Transfer software update to the CF card**, updates the programme version on the CF card. This function is actually only required for a new card where no data synchronisation has been carried out.

The function **Formatting the CF card** function in the vending machine enables the CPU to reformat the CF card. This is useful if there are read problems with the CF card.

Once the process is complete, the card can be safely removed via the Windows function Safely remove hardware and eject medium function and removed from the CF card reader.



Unauthorised removal of the card can damage it.

## Cancelling vending machines

As a rule, it is not necessary to delete a vending machine, so please be careful with this function. If necessary, a vending machine can be deactivated in the vending machine configuration.

You can delete a superfluous vending machine with **F5** or the menu item **Delete** menu item from the list.

## End

This ends the vending machine configuration.